

October 27, 2006

Revision: E

CadCamSystems

Support Document

Install New PAF File

The license file is known as the PAF. Anytime there is a change in your license (Examples: renew your maintenance, add new software, change dongles) you will receive a new PAF file by E-Mail. Together with your dongle your PAF will enable you to run your Delcam products. This file needs to be placed in the C:/dcam/config/pass folder on each computer using Delcam software. For a new software installation, you may need to create the pass folder first. Your PAF should not be edited or changed in any way or your software may not run. You can do an automatic or manual install:

AUTOMATIC INSTALL


The file with a .dcamlc extension is an automatic install script that will write the license file to the C:/dcam/config/pass folder on the computer.

1. Close any Delcam software you have running.
2. Move the current file dcam.paf to the 'Old' folder as a backup file.
3. Save the license file to your desktop, then double click to run. This will over write any dcam.paf file you currently have in your C:/dcam/config/pass folder.
4. Restart your Delcam software.

MANUAL INSTALL

The license file has a filename with a .paf extension.

1. Close any Delcam software you have running.
2. Move the current file dcam.paf to the 'Old' folder as a backup file. Then save the new file to C:/dcam/config/pass and rename it dcam.paf. Make sure you rename it exactly as shown in lowercase.
3. Restart your Delcam software.



CadCamSystems & Machining